LESSON 0

COMPILING/SIMULATING/DOWNLOADING A PANEL APPLICATION

17.1. C	ompiling an Application	1
	Compiling an Application	
	Building a Panel Runtime Package	
	Build a List Window	
17.2. Si	mulating an Application	3
17.2.1.	On-line/Off-line Simulation	3
17.2.2.	Simulating an Application	4
17.3. To	ransferring Data Between PC and Panel	5
17.3.1.	Downloading Data to Panel	5
	Uploading Data from Panel	
	Installing a USB Driver to Transfer Data Using a USB Cable	

17.1. Compiling an Application


Using the compiler offered by the software, you can verify the correctness of all the settings and designs, optimize the communication with the connected controllers, interpret macros into compact and ready-to-execute codes, and build the panel runtime data to be executed by the HMI engine of the target panel. The panel runtime data will be generated and saved into a PL2 file after the user compiles an application.

17.1.1. Compiling an Application

To compile an application, you can do the following:

- 1) In the menu bar, click Panel to bring up the Panel sub-menu. Click Compile... in the Panel sub-menu.
 - Alternatively, click the Compile icon in the main toolbar.
- 2) The Compile Panel Application dialog will pop-up and show the progress of the compiling process. If you want to cancel the compiling operation, click the Cancel button.

On the right is an example of the Compile Panel Application dialog in the process of compiling.




Compile Panel Application

? X

3) After the compilation is complete, the Compile Panel Application dialog will display the error count, warning count, and total file size of the panel runtime data. All the details will be listed in the Build List Window. To know about the Built List Window, please see <u>Section 17.1.3 Built List Window</u>.

On the right is an example of the Compile Panel Application dialog when the compilation is complete.



If the compilation is completed successfully, the runtime data of the current panel application will be saved into a file named Project Name_Application Name.pl2.

17.1.2. Building a Panel Runtime Package

A Panel Runtime Package includes the panel runtime data and system programs. To build a panel runtime package, you can do the following:


- 1) In the menu bar, click Panel to bring up the Panel sub-menu. Click Build Panel Runtime Package (PRP)...in the Panel sub-menu.
- 2) If the compilation is completed successfully, you will be asked to specify the file name in the Save As... dialog to save the package into a PRP file.

Note: The PRP file that includes the application and the system programs is portable. You can save the PRP file anywhere on the PC or a USB disk and download it to the target panel with the software or Data Transfer Helper (DTH).

17.1.3. Build a List Window

All the detailed information about the compiling process, error messages, and warning messages are listed in the Build List window. The Build List Window is a dockable window. In the window, error messages will have a red circle in front of the entry, and warning messages will have a yellow circle in front of the entry.

The following is an example of the Build List window:



You can right-click the Build List window to get the pop-up menu with the following menu items:


Menu Item	Description
Clear	Clears all the entries in the window.

17.2. Simulating an Application

Simulator is a convenient tool for design verification. With the simulator, you don't need to download the application to the target panel. On a PC, you can simulate how the application runs on the target panel.

There are two types of simulation offered by the software: On-line Simulation and Off-line Simulation.

17.2.1. On-line/Off-line Simulation



17.2.2. Simulating an Application

To simulate an application, you can do the following:

- 1) The application must be saved and compiled before the simulator can start.
- 2) Using the software:


In the menu bar, click Tools to bring up the Tools sub-menu. Click Run Off-line Simulation...in the Panel sub-menu.

Alternatively, click the Run Off-line Simulation icon in the main toolbar.

Using PanelSim.exe, an independent executable program:


Click Start->All Programs->"The software" -> PanelSim

3) In the PanelSim startup dialog, click Run button to start simulation



Note: When simulating an application in the software, the above dialog will show up and then close automatically before the simulation starts. In this case, ignore the dialog.

4) Simulate the application in the simulator window. The simulator window is similar in appearance to the target panel. The following is an example of the simulator window while running the application.



17.3. Transferring Data Between PC and Panel

In the software, you can transfer the panel runtime data using any of the Serial port, Ethernet port or USB client port whenever the target panel is running.


You can also use a Micro SD card or USB memory stick for the trouble-free update of the application.

17.3.1. Downloading Data to Panel

To download data by using the software, you may do the followings:

- In the menu bar, click Panel to bring up the Panel sub-menu. Click Download...in the Panel sub-menu.
 - Alternatively, click the Download icon on the standard toolbar.
- 2) In the Download Data to Panel dialog, select the options and settings before downloading.

The following is an example of the Download Data to Panel dialog.



Note: If the application is modified, the software will automatically compile the application before downloading.

The following table describes each property in the Download Data to Panel dialog.

Previous Data the selected data to be kept instead of being cleared after downloading.	want to			
download them. Available only when the data source is the current panel application. You can select the configuration data to backup the panel application to the target panel. format is the same as the Panel Application Files(PLF) Keep Previous Data Check the previous data of User Data (\$N), Alarm History, Recipe Data or Sampled Data if your the selected data to be kept instead of being cleared after downloading.	Γhe data			
Previous Data the selected data to be kept instead of being cleared after downloading.	ou want			
 The previous application was compiled and downloaded by the software V1.2.26 or later. The configurations of battery backed user memory, recipe blocks, data loggers, alarm blo the alarm logging buffer for both the old and new applications are exactly the same. 	The selected data will be kept only if: 1) The previous application was compiled and downloaded by the software V1.2.26 or later. 2) The configurations of battery backed user memory, recipe blocks, data loggers, alarm blocks, and			
Link Settings Select the communication port that is used to download the data.				
Communication Port Description				
Use the serial port to perform the download and selection communication port and the baud rate used. COM Ethernet Port: Communications Port (COM1) Baudrate: 115200	ct the			
Ethernet Use the Ethernet to perform the download. Type the IP Address the target panel is located, or choose a recently connected ent the list. COM © Ethernet IP Address: 192.168.10.84 PV121-TNT				
USB Use the USB to perform the download. You need to install the driver before transferring data with the USB cable. To know install a USB driver, please see Section 17.3.3				
If the target panel has sufficient memory, you can perform data transmission in safe mode.	If the target panel has sufficient memory, you can perform data transmission in safe mode.			
Mode Description				
Direct Mode Download data directly to flash memory.				
Safe Mode Buffer the data in the RAM of the target panel to prevent do problems in large files. The transmission has to be done succeived before the data in the SDRAM will be saved to the flash memory	essfully			
Status Display the transmission status and progress.	n status and progress.			
Start Click the button to start download the data.	Click the button to start download the data.			
Cancel Cancel the download operation.	Cancel the download operation.			
Close Exit the dialog.	Exit the dialog.			


Note: On the standard toolbar, you can click the Download Immediately icon to immediately download data using the existing settings of the Download Data to Panel dialog to the target panel.

17.3.2. Uploading Data from Panel

To upload data using the software, you may do the following:

- In the menu bar, click Panel to bring up the Panel sub-menu, then cick Upload... in the Panel sub-menu.
- In the Upload Data from Panel dialog, select the options and settings before uploading

The following is an example of the Upload Data from Panel dialog.



Note: If the application is modified, the software will automatically compile the application before downloading.

The following table describes each property in the Upload Data from Panel dialog

The following table describes each property in the Upload Data from Panel dialog.				
Property	Description			
Upload	Select the data you want to upload and save the uploaded data to the specified file. You can import existing panel applications from the configuration data file (PLF file).			
Link Settings	gs Select the communication port that is used to upload the data.			
	Communication Port	Description		
	СОМ	Use the serial port to perform the upload and select the communication port and the baud rate used.		
		ODM ○ Ethernet		
		Port: Communications Port (COM1)		
		Baudrate: 115200 💌		
	Ethernet	Use the Ethernet to perform the upload. Type the IP Address where the target panel is located, or choose a recently connected entry from the list.		
		○ COM		
		IP Address: 192.168.10.84 PV121-TNT		
	USB	Use the USB to perform the upload. You need to install the USB driver before transferring data with the USB cable. To know how to install a USB driver, please see <u>Section 17.3.3</u>		
Status	Display the transmission status and progress.			
Start	Click the button to start uploading the data.			
Cancel	Cancel the upload operation.			
Close	Exit the dialog.			

17.3.3. Installing a USB Driver to Transfer Data Using a USB Cable


This section describes how to install a USB driver for downloading an application to the target panel on a Microsoft Windows based computer.

- **Step 1:** Log on to your computer as an administrator.
- Step 2: Connect the computer and the target panel through a USB cable
- Step 3: Start installing the driver

You can use one of the following methods as appropriate to begin installing the driver:

■ With the Found New Hardware Wizard


Power on the target panel, "Found New Hardware Wizard" will automatically pop-up in Windows to guide you to install the driver.



■ With the Upgrade Device Driver Wizard

If the "Found New Hardware Wizard" does not appear or if it is turned off, you can do the followign to bring out the Upgrade Device Driver wizard:

- 1. On the desktop, right-click My Computer, and then click Manage.
- Under System Tools, click Device Manager.
 The devices that are installed on the computer are listed in the right pane.
- 3. Expand the **Other devices** category
- 4. Right-click the device named **Neo HMI** for which you want to install the driver, and then click **Properties**.




5. Click the **Driver** tab, and then click **Update Driver**. The Upgrade Device Driver wizard starts.

Step 4: Install the driver by following the wizard instructions


1. Click Next.



2. Click Install from a list or specific location (Advanced), and then click Next.



- 3. Click Search for the best driver in these locations, and then select Include this location in the search, click Browse, select \Usb in the software's installation folder as the folder that contains drivers, and then click Next.
- 4. Click Continue Anyway if the Hardware Installation dialog box shown as below appears.





Step 5: Click Finish to complete installing the driver for Neo HMI



Note: The first time you connect a target panel that plugs into any of the USB ports on the computer, you need to install a driver for that device.

After installing the driver, you can use the USB to transfer data between the PC and the target panel which supports USB transferring. In the software, you need to select USB as the link settings in the Download Data to Panel/Upload Data from Panel dialog box before transferring.